

Breaker v3.10 for Win32

Program Description	<p>The Breaker program splits a larger file into smaller components, suitable for copying via floppy or ZIP disk, or even for file transfers. It is NOT like the older PKZIP, which requires floppies, but it is not as pretty either.</p> <p>The Breaker program simply reads the source file as a binary file and writes smaller chunks with the filenames of BPART.000, BPART.001, etc. The actual file name is not stored, and should be otherwise transferred.</p>
Platform and Package	Win32 Console; Goldstar Utility & Management Package
Pricing	FREE
Command Line Syntax and Help Screen	<p>BREAKER Version 3.10: 07/17 (C)2018 Goldstar Software Inc.</p> <p>Usage: BREAKER pathname [drv:] [/C] [/3 /5] [/D] [/T B S]</p> <p>This command breaks a file into pieces to fit on a set of floppy disks. The file pieces are written directly to the specified drive drv:, or A:.</p> <p>/C Specifies Continuous operation (No Keypresses) for network use.</p> <p>/3 Specifies 3.5" disks. (Default)</p> <p>/5 Specifies 5.25" disks.</p> <p>/D Specifies Double Density. (Default is High)</p> <p>/T Specifies Tiny (32K) Parts. (Forces Continuous Mode)</p> <p>/B Specifies Big (14MB) Parts.</p> <p>/S Specifies Super (140M) Parts.</p> <p>/G Specifies Gigantic (650M) Parts.</p>
Examples and Sample Usage	<p>Breaker splits a specified file into pieces on the target drive. Specify the /C option when splitting to network or a hard drive, to avoid having to hit a key between each part.</p>
Other Information	<p>Breaker is part of the Goldstar Utility & Management Package.</p> <p>For more information on these utilities contact us at www.goldstarsoftware.com</p>
Version History	<p>Version 2.1: First documented version</p> <p>Version 2.2: Added support for Gigantic (CDROM-sized) parts.</p> <p>Version 3.0: Added GSLic capabilities; created evaluation download.</p> <p>Version 3.01: Updated licensing code.</p> <p>Version 3.10: Removed license code and made this a FREE utility.</p>
Known Problems	None.