

MV-90 xi Product Marketing Update

Topic: Windows 7 Support

Date: September 27, 2010

From: Pam Sen

Itron is now supporting MV-90 xi on specified editions of the Windows 7 operating system.

MV-90 xi v3.0 is approved for use on the 32- and 64-bit Professional and Enterprise editions of Windows 7. MV-90 xi v2.0 SP1 can be installed on the 32-bit Professional and Enterprise editions of Windows 7.

Also permitted is the use of MV-90 xi v3.0 on the 64-bit Windows 2008 Server operating system.

This table summarizes the versions of operating systems and Pervasive PSQL that are currently supported for use with MV-90 xi. Version 1.0 of MV-90 xi is not listed, as support for v1.0 will end effective September 30th.

Server Operating Systems	MV-90 xi Version		
	1.5	2.0 SP1	3.0
Windows 2000 Server	✓		
Windows 2003 Server	✓	✓	✓
Windows 2008 Server – 32-bit		✓	✓
Windows 2008 Server – 64-bit			✓
Workstation Operating Systems	1.5	2.0 SP1	3.0
Windows 2000 Professional	✓		
Windows XP – SP 2 or higher	✓	✓	✓
Windows Vista – Business & Enterprise		✓	✓
Windows 7 – Professional & Enterprise - 32-bit		✓	✓
Windows 7 – Professional & Enterprise - 64-bit			✓
Windows 2003 Server		✓	✓
Windows 2008 Server – 32-bit		✓	✓
Windows 2008 Server – 64-bit			✓
Database Software	1.5	2.0 SP1	3.0
Pervasive PSQL v8.5, v8.6, v8.7	✓		
Pervasive PSQL v9.5 *	✓	✓	✓
Pervasive PSQL v10 (Summit)		✓	✓

* For MV-90 xi v3.0, the free upgrade from PSQL v9.x to v9.71 must be applied.

Only the 32-bit version of Pervasive PSQL is supported for use with MV-90 xi. Even if you are running a 64-bit operating system, you must use a 32-bit version of PSQL. Windows 2008 Server, Vista, and 7 operating systems require the use of PSQL v10.

The support of 64-bit operating systems required updates to the MV-90 xi v3.0 installation program. The latest installation program on Itron Access works for both 32-bit and 64-bit installations. This file is dated September 2010.

Installing MV-90 xi on Windows 7 and 2008 Server requires additional steps. The document detailing these steps, ***MV-90 xi Supplemental Installation Instructions for Windows 7 and 2008***, is available on Itron Access. This document applies to both MV-90 xi v3.0 and v2.0 SP1. Updated Installation and Update Guides for MV-90 xi v3.0 are also posted on Itron Access.

Some program modifications were required to MV-90 xi, including changes to the System Dashboard component. After completing the installation steps, please go to Itron Access and download the latest Multi-File Download (MFD) for your version of MV-90 xi.

Reminders

Prices on new licenses and upgrades to Pervasive PSQL v10 are increasing effective October 1st. Goldstar Software (www.goldstarsoftware.com) is our preferred reseller of Pervasive products, though you can buy PSQL through Itron or other resellers as well.

Support for MV-90 xi v1.0 ends on September 30th.

Questions

If you have questions about Windows 7 support, please contact Pam Sen or your regional Itron Support Services team.